

**SHORTCUT KEY List - ZofzPCB 0.5.0012**

	Description	Ctrl +	Description
Esc	Remove distance markers, Remove net highlights, Exit from menus		
F1	Toggle keyboard Help On/Off		
F2	Toggle Fullscreen On/Off		
F3	Emulates mouse wheel roll action +/- layer peel or spread - Depend on layer mode		
F4	Emulates mouse wheel roll action +/- layer peel or spread - Depend on layer mode		
F5	Set Zoom Mode	F5	Reset Peel/Spread mode and set Zoom Mode
F6	Set Layer Peel Mode ( works on both sides independently )	F6	Reset Peel/Spread mode and set Peel Mode
F7	Set Layer Spread Mode	F7	Reset Peel/Spread mode and set Spread Mode
1	Go to position marker "1"	1	Save position marker "1"
2	Go to position marker "2"	2	Save position marker "2"
3	Go to position marker "3"	3	Save position marker "3"
4	Go to position marker "4"	4	Save position marker "4"
5	Go to position marker "5"	5	Save position marker "5"
6	Go to position marker "6"	6	Save position marker "6"
7	Go to position marker "7"	7	Save position marker "7"
8	Go to position marker "8"	8	Save position marker "8"
9	Go to position marker "9"	9	Save position marker "9"
TAB	Level camera horizontally ( set camera tripod direction normal to PCB )		
W	Camera Pitch Down		
S	Camera Pitch UP		
A	Camera Yaw Left		
D	Camera Yaw Right		
Z	Flip PCB to other side		
X	Center PCB without Rotation		
Space Bar	Rotate camera to nearest rectangular angle		
Space Bar	With active Layer Bar, toggle state of last selected item		
E	Set measurement Marker at the shape Edge pointed by the mouse pointer		
P	Set measurement Marker at the Pad pointed by the mouse pointer		
P	In CrossCheck mode using CPN method: CrossProbe selected component Pin		
H	Set measurement Marker at the Hole ( drill ) center pointed by the mouse pointer		
N	Highlight Net pointed by the mouse pointer	N	Select next selection graphical effect
N	In CrossCheck mode using "CPN" method: CrossProbe selected Net		
C	In CrossCheck mode using "CPN" method: CrossProbe selected Component	C	Copy content of measurement text to the clipboard
C	In CrossCheck mode using "C" method: CrossProbe selected Component, Pin, Net		
←	Move Camera left	←	Move slowly Camera left
→	Move Camera right	→	Move slowly Camera right
↑	Move Camera up	↑	Move slowly Camera up
↓	Move Camera down	↓	Move slowly Camera down
INS	Toggle 3D Mouse mode between camera mode and object mode		
Home	Position camera in front of the PCB	Home	Position camera in front of the PCB and reset rotation
Page Up	Move camera forward	Page Up	Move slowly camera forward
Page Down	Move camera backward	Page Down	Move slowly camera backward
/	Roll camera counterclockwise	/	Rolls counterclockwise PCB to the nearest rectangular position
*	Roll camera clockwise	*	Rolls clockwise PCB to the nearest rectangular position
LMB	Zoom center at mouse pointer		
LMB & Drag	Rolls PCB	LMB & Drag	Rotate PCB at mouse pointer
RMB & Drag	Enable PCB shift ( x+ y )		
Shift + LMB & Drag	Enable PCB shift ( x+ y )		
Shift + RMB & Drag	Rotate Camera		
Double LMB	Double LMB on Layer Bar enter Peel Mode and display only selected layer		
Double MMB	Reset Peel/Spread mode		
RMB	Floating Menu		
Del	PCB Cut Section at mouse pointer		
Mouse Mov. & Del	Dinamically move cut section point of PCB		
Mouse Wheel	Zoom In/Out or layer peel or layer spread - Depend on layer mode		